

How to fix emacs problems with Backspace or Delete

How to fix emacs problems with Backspace or Delete

If your "delete" key on the terminal you're using isn't acting as you expect it to, it is likely that it is sending the "backspace" character instead of the "delete" character that is expected. This is a common problem with PC's and Macs. There are a few things you can do about this (in order of preference):

- see if you can tell your terminal emulator (the communications program on your MAC or PC) to use "control-?" when you hit the "backspace" key.
- you tell athena what to expect for the backspace key. To do this, put the following line in your .startup.tty file:

```
stty erase "^H"  
or stty erase "^?"
```

depending on which of these you normally see when you hit your backspace key.

That will give you backspace capabilities in everything but emacs. In emacs, add the following lines to your .emacs file (create one if you don't have one, as above):

```
(setq term-setup-hook  
'(lambda ()  
  (setq keyboard-translate-table "\C-@\C-a\C-b\C-c\C-d\C-e\C-f\C-g\C-?")  
  (global-set-key "\M-h" 'help-for-help)))
```

That will fix the backspace key, and set "M-h" to give you help (regularly c-h does that).