

# Installing Mastercam to run off the IS&T License Server

## Installing Mastercam to run off the IS&T License Server

On this page:

[Requirements](#)  
[Installing Mastercam](#)  
[Instructions](#)  
[See Also](#)

### Requirements

This Mastercam installation procedure is only authorized for faculty/staff/student users at MIT.

#### Note:

- You will not need to register with Mastercam or download anything from their web site.
- Running Mastercam this way requires that you maintain network connectivity, and requires use of the [MIT VPN](#) if you are off the MIT campus.
- Mastercam 2019 and 2020 will ONLY run on Win 64bit operating system

### Installing Mastercam

#### Instructions

1. Download the appropriate Mastercam installation from the Software Grid.
2. Double-click on the downloaded .exe file to run the installer.
3. At the end of the installation, deselect the **run Mastercam** option and exit the installer.
4. Then
  - Windows 10 - Select Start > CodeMeter > CodeMeter Control Center
  - Windows 7/8 - Select Start > All Programs > CodeMeter > CodeMeter Control Center
5. In the Code Meter Control Center dialog box, select **WebAdmin**. Your default browser then displays the CodeMeter WebAdmin website.
6. Select **Configuration**.
7. Select Add new server.
8. Enter **mastercam.mit.edu** and then click Add.
9. Select **Add New Server**.
10. Enter **w92-mastercam.mit.edu** and then click Add.
11. Click **Apply**, and close the Code Meter WebAdmin website.

Mastercam should now launch. This initial launch will create the file structure where the Course Specific Files will be distributed. Students enrolled in 2.008 can now follow the instructions posted on the 2.008 course website to load the Course Specific files shared with you through Dropbox by the lab instructor.

### See Also

- [Mastercam Landing Page](#)